

Direct and PROCEDURE Workplan Commands

Below are the Object Handler commands provided to maintain workplans of the type PROCEDURE. See Direct and PROCEDURE Workplan Syntax for an explanation of the Natural Object Handler clauses mentioned below.

DIRECT

The DIRECT clause may contain any of the commands used with the NATLOAD, NATUNLD and SYSTRANS utilities. If you specify more than one direct command, enter a semicolon (;) between the commands to separate them from one another.

EXECUTE (*procedure-workplan*)

Executes a workplan of the type PROCEDURE.

UNLOAD *select-clause* [*parameter-setting*] [*option-setting*]

Unloads the objects defined in the Select-Clause with the parameters defined in Parameter-Setting with the options defined in Option-Setting.

LOAD *select-clause* [*parameter-setting*] [*option-setting*]

Loads the objects defined in the Select-Clause with the parameters defined in Parameter-Setting with the options defined in Option-Setting.

LOADALL [*parameter-setting*] [*option-setting*]

Loads all objects from the work file with the parameters defined in Parameter-Setting with the options defined in Option-Setting.

SCAN *select-clause* [*option-setting*]

Scans the work file for the objects defined in the Select-Clause with the parameters defined in Parameter-Setting with the options defined in Option-Setting.

SCANALL [*option-setting*]

Scans the work file for all objects with the parameters defined in Parameter-Setting with the options defined in Option-Setting.

DELETE *select-clause* [*option-setting*]

Deletes the objects defined in the Select-Clause with the options defined in Option-Setting.

Restrictions:

Delete FDT is not possible.

FIND *select-clause* [*option-setting*]

Finds the objects defined in the Select-Clause and writes them into Work File 3 or into the file name specified. In addition, a report of the objects found can be written into Work File 4 or another report file specified.

FINDLIB *select-clause* [*option-setting*]

Finds the libraries for Natural objects or Natural command processor sources defined in the Select-Clause and writes them into Work File 3 or to the file name specified. In addition, a report of the objects found can be written into Work File 4 or another report file specified.

RESTART [*file-name*]

Continues an interrupted load function. This is only possible if information was written into a restart file during the aborted load. Restart load information may be written to Work File 6 (*file-name*). See also RESTART under OPTION-Clause in Option-Setting (Direct and PROCEDURE Workplan Syntax, Commands).